

Feature	Description	Benefit
Recognition Improvements		
Full support for € and £ symbols	Recognition support (in both ICR and OCR) for the British Pound symbol and the European Euro symbol. The support includes currency formatting, verification, and output/merge.	<ul style="list-style-type: none"> • These European symbols will be recognized in both machine and handprint formats • Better accuracy for non-US implementations • Increase user productivity
Improved OCR-A	OCR-A of special characters is fully functioning and selectable by the user.	<ul style="list-style-type: none"> • Full OCR-A character set recognition
Location Improvements	Improve location on existing forms and use of “for location only” explicit IDs.	<ul style="list-style-type: none"> • Improved recognition for Existing forms • Forms using a forced form ID get the benefit of Explicit ID’s ‘for location only’ aid in location of fields on the drop out form
Lexical checking codes in image zones	Regular expression allows specification for the expected value in the image zone.	<ul style="list-style-type: none"> • Better accuracy in image zone recognition and specification
New barcode formats	Recognition support for EAN/UCC 128 (recognition + pre-fill), ISBN Add-on 2 and 5 (recognition + pre-fill), Patch code (recognition only), Industrial, Datalogic, Matrix, IATA 2/5 (recognition only).	<ul style="list-style-type: none"> • Recognition of more barcode types
Export of image zones in color	Color clips can be exported from image zones.	<ul style="list-style-type: none"> • Image clips from Image Zones can now be viewed and stored with better accuracy
Usability Improvements		
Allow selection of special characters	Allows the user to specify allowable special characters returned by RecoFlex engines. Note: The selections are not going to be filtered for electronic submissions.	<ul style="list-style-type: none"> • Greater accuracy because only the valid special characters for a field can be selected as part of the recognition set • Dialog added for easier selection
Batch explorer multi-select	Support multiple selection in the Batch Explorer. Operations such as Discard and Accept can be performed on multiple batches.	<ul style="list-style-type: none"> • Simplify actions on multiple batches • Increase user productivity
Enhanced Alert notification options for Control Center	When an alert is triggered in Control Center (Enterprise Only), a user can be notified by email, NT event log record, or an execution of a command line.	<ul style="list-style-type: none"> • Control Center does not need to be monitored as a separate application. Administrators for <i>TELEform</i> will be able to customize how alerts are delivered to them.
USB key certification	USB hardware keys are now certified for licensing. Version 8.2 only.	<ul style="list-style-type: none"> • Parallel keys are sent by default. USB keys can be ordered with approval from Sales Management.
Documentation Changes and Additions		
Enhanced documentation on using TF for Document Capture	Capture chapter to the User Guide. Online capture tutorial.	<ul style="list-style-type: none"> • Better visibility of Capture capabilities
TF/LO compatibility doc	A guide explaining how TF and LO work together	<ul style="list-style-type: none"> • Quick source for interoperability
Connect Agent document	A single guide for all Export Connect Agents.	<ul style="list-style-type: none"> • One guide for all Export Connect Agents • Simplified help for Export Connect Agent creation